



Step 1

From the Main Menu Select System



Step 2


Select Account → Click on the modify icon to change User Name and Password



Note: You cannot modify the systems defaulted User Names.

Step 3


Click on User Name drop down menu and choose User Name to Modify



The screenshot shows the 'Modify User' window. The 'User Name' dropdown menu is open, displaying three options: 'admin', 'admin', and 'default'. The first 'admin' option is highlighted with a red box. Other fields include 'Modify Password' (888888), 'Old Password', 'New Password', 'Confirm Password', 'Period' (Set), 'User MAC', 'User Name' (admin), 'Group' (admin), and 'Memo' (test user). The 'Authority' section is visible with tabs for System, Playback, and Monitor, each containing a list of checked permissions.

Step 4

Check Modify Password → Input old password



The screenshot shows the 'Modify User' window with the 'Modify Password' checkbox checked (highlighted with a red box). The 'Old Password' field is filled with seven dots. A keyboard overlay is present, with the 'Enter' key highlighted (highlighted with a red box). Other fields include 'User Name' (admin), 'User MAC', 'User Name' (admin), and 'Memo' (test user). The 'Authority' section is visible with tabs for System, Playback, and Monitor, each containing a list of checked permissions.

Step 5

Input New Password and Confirm New Password. Click Save.

The screenshot displays the 'Modify User' configuration page. The 'User Name' is set to 'admin'. The 'Modify Password' checkbox is checked. The 'Old Password' field contains six dots. The 'New Password' and 'Confirm Password' fields, both containing six dots, are highlighted with a red box. A virtual keyboard is overlaid on the page. Below the password fields is a list of permissions, all of which are checked: All, ACCOUNT, PTZ, COLOR, CAMERA, SYSTEM, INFO, STORAGE, CLEAR LOG, DISCONNECT USER, MANUAL CONTROL, EVENT, SHUTDOWN, DEFAULT&UPGRADE, BACKUP, and NETWORK. At the bottom right, the 'Save' button is highlighted with a red box, and the 'Cancel' button is visible next to it.

Modify User

User Name: admin

Modify Password:

Old Password:

New Password:

Confirm Password:

User MAC:

User Name: admin

Group: admin

Memo: test user

All

ACCOUNT

PTZ

COLOR

CAMERA

SYSTEM

INFO

STORAGE

CLEAR LOG

DISCONNECT USER

MANUAL CONTROL

EVENT

SHUTDOWN

DEFAULT&UPGRADE

BACKUP

NETWORK

Save Cancel